Procedure to install the parking lot and the areas of standstill on TomTom for Pocket PC or SmartPhone

The database of the points of interest is constituted by: two files with extension OV2 Areas of standstill Ania.ov2, Parking lot Ania.ov2, and two files combined with extension BMP Areas of standstill Ania.bmp, and Parking lot Ania.bmp.

Phase 1 Download the files of the points of interest
Download the zip file of the point of interest.
When it is required, click on "Safe" to save the file on the computer. Extract the files inside a directory, for instance in desktop or documents.

Phase 2 Connect your device to the PC through ActiveSync
The Pockect PC is connected if the icon of ActiveSync visualized in the bar of the activities is green.
You can find ActiveSync on the Microsoft web site at the address:.....

Phase 3 Copy the files of the points of interest from the PC
Access the directory of the local disk of the PC in which the files have been drawn out from the database of the areas of standstill Ania.ov2/Parking lot Ania.ov2 and Areas of standstill Ania bmp/Parking lot Ania. Bmp. Select and Copy on both the files.

Phase 4 Copy the files of the points of interest on the Pocket PC
Enter from resources of the computer inside the portable device GPS. Enter therefore to the card of memory if the map has been installed on the card of memory.
If the map is installed on the memory of the Pocket PC select Documents and the name of the maps of Italy.
Once entered the directory of the maps Italy glue the files of the points of interest inside the directory. Now the files of the points of interest are copied inside the directory.
You are ready to utilize the new points of interest on Pocket PC.

Installation of the Parking lot and the Areas of standstill point on TomTom GO

The database of the points of interest is constituted by: two files with extension OV2 Areas of standstill Ania.ov2, Parking lot Ania.ov2, and two files combined with extension BMP Areas of standstill Ania.bmp, and Parking lot Ania.bmp.

Phase 1 Download the zip file of the point of interest.
When it is required, click on Safe to save the file on the computer. Extract the files inside a directory, for instance in desktop or documents. Extract the content of the file.

Phase 2 Connect TomTom GO to PC
Connect TomTom GO through cable USB. Check that TomTom GO is fed by the adapter CA.

Phase 3 Copy the files of the point of interest from PC
Access to the directory of the local disk of the PC in which the files have been drawn out from the database of the areas of standstill Ania.ov2/Parking lot Ania.ov2 and Areas of standstill Ania bmp/Parking lot Ania. Bmp. Select and Copy on both the files.

Phase 4 Copy the files of the points of interest on the TomTom GO
Enter from resources of the computer inside the portable device GPS. Enter therefore to the card of memory and enter to the map Italy. Once entered the directory of the maps Italy glue the files of the points of interest inside the directory. Now the files of the points of interest are copied inside the directory.
You are ready to utilize the new points of interest on Pocket PC